

XIRIUM PRO App & Firmware

Version history - Issues & solutions







Firmware on XIRIUM PRO device		Арр
App Control firmware NACF-Dec052014 released in December, 2015 - Initial release	XIRIUM PRO firmware 1.0 released in December, 2015 - Initial release	XIRIUM PRO app 1.0 released in December, 2015 - Initial release
	XIRIUM PRO firmware 1.1 released in February, 2016  Packet-loss indication Unlink support  XIRIUM PRO firmware 1.2 released in February, 2016  Bug fix	XIRIUM PRO app 1.1 released in February, 2016  - Monitoring signal strength and packet-loss - Unlink RX from TX; dragging to "available devices"
App Control firmware NACF-Oct222015 released in April, 2016 - Bug Fix	XIRIUM PRO firmware 2.0 released in April, 2016  Mute on RX Country specific settings Optimized battery algorithm and display Optimized RSSI display	XIRIUM PRO app 2.0 released in April, 2016  - Mute switch in RX EDIT mode - Country specific settings / Touring-option - Optimized battery algorithm and display - Optimized RSSI display
	XIRIUM PRO firmware 2.1 released in August, 2016 - Bug fix	XIRIUM PRO app 2.1 released in August 2016  - Bug fix - UAE included in zone 3
		XIRIUM PRO app 2.1.1 released in September, 2016 only an iOS release! - iOS 10 compatible
App Control firmware NACF-Aug122016 released in February, 2017 - Bug Fix  Latest version!	XIRIUM PRO firmware 3.0 released in February, 2017  - Advanced Mode - Device Temperature Indication	XIRIUM PRO app 3.0 released in February, 2017  - RF Attenuator - Hide SSID option - Device Temperature Indication - Bug fixes - Australia, New Zealand, Hong Kong included in zone 2



Firmware on XIRIUM PRO device		Арр
	XIRIUM PRO firmware 3.1 released in June, 2017  - Bug fixes - Optimizations - Adjusted Hardware Reset (sets attenuator to off)	XIRIUM PRO app 3.1 released in June, 2017 - support for FW 3.1
	XIRIUM PRO firmware 3.2 released in October, 2017  - Major Bug fixes - Optimizations  Latest version!	XIRIUM PRO app 3.2 released in October, 2017  - support for FW 3.2 - iOS 11 compatible - Mounting Guide update  Latest version!

## Neutrik strongly recommends to keep the devices and the app up-to-date!

Since App version 2.0 and FW version 2.0 every FW update will be communicated to users via the app. The user will be informed by the app store / play store if there is a new app version available. If the user downloads the latest app but uses an old firmware on the device there will be a message in the app with a recommendation to update the devices to make use of all the new features in the app.